

OATMEAL STOUT (Partial Mash)

Official NORTHERN BREWER Instructional Document

Who doesn't love oatmeal stout? It's impossible not to love oatmeal stout. Full-bodied with a silken texture and a gentler roast profile than their Irish and American cousins, this ebony ale is rich and substantial. Almost hidden under strong notes of dark chocolate, figs, and light-roast coffee you'll find a subtle nutty, grainy flavor from flaked oats (made possible by the partial-mash technique). A long-lasting raft of beige foam floats on the jet-colored pint and laces the glass all the way down. This stout is wonderful by itself, but if you're looking for a dessert beer pair it up against a flourless chocolate cake, truffles, or even a raspberry tart.

O.G.: 1.049 READY: 6 WEEKS

1-2 weeks primary, 2-4 weeks secondary
1-2 weeks bottle conditioning

KIT INVENTORY:

SPECIALTY GRAIN

- 2.5 lbs Maris Otter
- 0.5 lbs Black Malt
- 0.5 lbs English Dark Crystal
- 0.5 lbs flaked oats

FERMENTABLES

- 3.15 lbs Dark malt syrup
- 1 lb Briess Dark dry malt extract

HOPS & FLAVORINGS

- 2 oz US Fuggle (60 min)

YEAST

- **WYEAST 1945 NB NEOBRITANNIA.** Flocculation: Moderate-high. Attenuation: 72-77%. Temperature Range: 66-74 F.
- **DRY YEAST ALTERNATIVE: SAFALE S-04 ALE YEAST.** Optimum temp: 64-75° F

BEFORE YOU BEGIN ...

MINIMUM REQUIREMENTS

- Homebrewing starter kit for brewing 5 gallon batches
- Two kettles, one of at least 4 gallons capacity and one of at least 2 gallons
- A large mesh bag or strainer that can hold 5 lbs of grain
- A thermometer with a range that includes 120-170°F
- A 5 gallon glass carboy, with bung and airlock, to use as a secondary fermenter - If you do not have a secondary fermenter you may skip the secondary fermentation and add an additional week to primary fermentation before bottling
- Approximately two cases of either 12 oz or 22 oz pry-off style beer bottles

UNPACK THE KIT

- Refrigerate the yeast upon arrival
- Locate the Kit Inventory (above) - this is the recipe for your beer, so keep it handy
- Doublecheck the box contents vs. the Kit Inventory
- Contact us immediately if you have any questions or concerns!

PARTIAL MASH BASICS

- This partial mash kit uses some techniques that may be unfamiliar to the extract brewer. The idea behind partial mash brewing is to use some malt extract for sugar content along with extracting some sugars yourself directly from grains. Basically, you'll be putting the grains in water and holding the mixture (called the mash) at a particular temperature while enzymes in the grain break complex starches down into simpler sugars. Then you will rinse the grains with hot water (a process called sparging) to get as much of the sugar off as possible. The liquid that you collect should be a sweet wort that you can use as a base for adding malt extract and hops. The procedure below will take you through the process step by step.

PROCEDURE

A FEW DAYS BEFORE BREWING DAY

1. Remove the liquid Wyeast pack from the refrigerator, and "smack" as shown on the back of the yeast package. Leave it in a warm place (70-80° F) to incubate until the pack begins to inflate. Allow at least 3 hours for inflation; some packs may take up to several days to show inflation. Do not brew with inactive yeast - we can replace the yeast, but not a batch that fails to ferment properly. If you are using dry yeast, no action is needed.

ON BREWING DAY

2. Heat 5 quarts of water to 164°F in your mash kettle.

3. Crush the grains if they are unmilled. Pour crushed grain and oats into your nylon mesh bag and place in the kettle, or if you are not using a nylon bag pour the grain directly into your mash kettle.

4. Adjust the temperature. Take a temperature reading of the mixture. The temperature should be within 1-2°F of 154°F. If not, adjust by adding cold or hot water as needed.

5. Put the lid on your mash kettle and wrap it in old towels or blankets to insulate it, or put it in an oven set to "warm" or "low" to maintain the temperature (make sure your oven is not too hot! The temperature of the oven should be at or under 154°F). Leave for one hour.

6. While the mash rests, collect and heat sparge water in your second pot. Collect 5 quarts of water and heat to 170°F. Hold at this temperature until the mash is finished.

7. When the one hour mash is finished, return the mash kettle to the stove (without towels!) and apply very low heat. Raise the temperature of the mash to 170°F, being careful not to scorch the grains.

8. Separate the grain from the liquid portion of the mash. Remove the grains from the mash - don't spill or waste the liquid, which is now the wort. If using a mesh bag, you can simply lift it out. If not using a mesh bag, scoop the grain into a colander or sieve over a bowl or pan to collect the drips. If you are using a separate kettle to boil with, pour the wort from the mash kettle to the boil kettle.

9. Sparge the grain. Using a strainer or mesh bag, hold the grain over the wort in the kettle. Slowly pour the 170° F sparge water through the grain, one quart at a time, until it's gone. Collect the sparge water along with the wort in the boil kettle. When finished, you may discard the grain.

10. Top up the kettle. Add more water if necessary to achieve your normal boil volume.

11. Bring to a boil and add in 3.15 lbs of Dark malt syrup and 1 lb of Briess dark dry malt extract. Remove the kettle from the burner and stir in the Dark malt syrup and Dark DME, then bring back up to a boil.

- Add 2 oz US Fuggle hops and boil for 60 minutes.

12. Cool the wort. When the 60-minute boil is finished, cool the wort to approximately 100° F as rapidly as possible. Use a wort chiller, or put the kettle in an ice bath in your sink.

13. Sanitize fermenting equipment and yeast pack. While the wort cools, sanitize the fermenting equipment - fermenter, lid or stopper, fermentation lock, funnel, etc - along with the yeast pack and a pair of scissors.

14. Pour the cooled wort into your fermenter. Leave any thick sludge in the bottom of the kettle.

15. Add cold water as needed to bring the volume to 5 gallons.

16. Aerate the wort. Seal the fermenter and rock back and forth to splash for a few minutes, or use an aeration system and diffusion stone.

17. Measure specific gravity of the wort with a hydrometer and record.

18. Add yeast once the temperature of the wort is 78°F or lower (not warm to the touch). Use the sanitized scissors to cut off a corner of the yeast pack, and carefully pour the yeast into the primary fermenter.

19. Seal the fermenter. Add approximately 1 tablespoon of water to the sanitized fermentation lock. Insert the lock into rubber stopper or lid, and seal the fermenter.

20. Move the fermenter to a warm, dark, quiet spot until fermentation begins.

BEYOND BREWING DAY, WEEKS 1-2

21. Fermentation should begin within 48 hours. The optimum fermentation temperature for this beer is 64-74° F - move the fermenter to a warmer or cooler spot as needed.

BEYOND BREWING DAY- SECONDARY FERMENTATION

22. Active fermentation should complete within 1-2 weeks, after which you can transfer your beer to a sanitized secondary fermenter for 2-4 weeks conditioning.

BOTTLING DAY-ABOUT 1 MONTH AFTER BREWING DAY

23. When you are ready to bottle, sanitize siphoning and bottling equipment and mix a priming solution. Use the following amounts, depending on which type of sugar you will use:

- Corn sugar (dextrose) 2/3 cup in 16 oz water.

- Table sugar (sucrose) 5/8 cup in 16 oz water.

Then bring the solution to a boil and pour into the empty bottling bucket.

24. Siphon beer into bottling bucket and mix with priming solution. Stir gently to mix, don't splash.

25. Fill and cap bottles.

1-2 WEEKS AFTER BOTTLING DAY

26. Condition bottles at room temperature for 1-2 weeks. After this point, the bottles can be stored cool or cold.

27. Serving. Pour into a clean glass, being careful to leave the layer of sediment at the bottom of the bottle. Cheers!